



© 2012-2020 by SOP - All Rights Reserved
This document is protected by EU copyright and
other intellectual property laws and may not be reproduced,
rewritten, distributed, re-disseminated, transmitted, displayed,
published or broadcast, directly or indirectly, in any medium
without the prior written permission of SoP.

www.soundsofplanet.com
Executive Producer/Editor: Grzegorz Marciak

Sounds of Planet would like to thank you for purchase of sound set called EXs 178 Guitar Collection for Kronos.

This sound set offers the highest quality samples of extraordinary instruments such as:

- Classic Guitar
- Acoustic Guitar
- Jazz Guitar
- Electric Guitar
- Electric Bass
-

All samples have been processed using 24-bit technology.

Exs 178 Guitar Collection from Sounds of Planet contains set of sounds consisting of:

- 128 Programs
- 75 multisamples
- 590 MB of disc space
- 47 MB of virtual memory

Available controllers have been programmed to each program as well as four Karma scenes including Drumtrack.

The first records about the guitar had appeared already in the XIII-th century. Initially guitar had four strings, in XV-th century the fifth string was added and in XVIII-th century, the sixth string has been added. In its long history, guitar had its ups and downs. Peak period, when acoustic guitar reverberated both in parlours and concert halls was so called "golden period of the guitar" falling on the I-st half of XIX-th century. Guitar was one of the first instruments, for which it was possible to amplify the sound. Thus, electric guitar was popularized in the 1930s of XX-th century. The whole XX-th century was great development of electric guitar as well as appearance of electric bass guitar. Look and design have been evaluating until today. Popular songs, in which guitar plays the main role, improvised solo parts as well as instrumental compositions played live and present on numerous records are still endless source of inspiration.

Make a copy of all own files in the instrument performing SAVE ALL function- see manual KRONOS_Quick_Starts or KRONOS_Param_Guide.

The following instructions are copied from the Kronos Parameter Guide for your convenience:
To install an EXs:

1. If you downloaded the EXs data, un - zip the downloaded file. Un - zipping the archive will result in a folder containing several different files. Note: Depending on your browser settings, the downloaded file may be unzipped automatically. One of the files in the resulting folder has a name which ends with "tar.gz." Please do not un - zip this tar.gz file.
2. Copy the un - zipped folder to a USB storage device.
3. Safely disconnect the USB storage device from your computer.
4. Connect the USB storage device to the KRONOS.
5. Go to the Disk Utility page.
6. Using the Drive Select menu at the bottom of the page, select the USB storage device. You may need to wait a few seconds after connecting the device before it is recognized.

7. Open the folder containing the EXs data from step 2.

8. Select the file whose name ends in .exsins. The “exsins” suffix stands for “EXS Installer.” For instance, an installer file might be named “EXs178.exsins.” When an .exsins file is selected, the Load button changes to read Install. Only one EXs can be installed at a time. If Multiple Select is On, Install will be disabled.

9. Select Install EXs from the menu, or press the Install button. The system will check to confirm that the installation files are valid, and that there is sufficient space on the SSD to install the EXs. Next, a dialog box will appear:

Found installer for: [EXs name]

Space required: [nnn] MB

SSD1: [disk name] [nnn] GB available

10. Press Install to continue with the installation, or press Cancel to stop without installing. An “are you sure?” message will appear to confirm the installation.

11. Press OK to continue with the installation, or press Cancel to stop without installing. The installation will then begin. This may take a while; a progress bar shows the installation as it proceeds. Next, the newly installed files will be verified. After the verification has completed successfully, the progress bar will disappear, and the installation is complete. The EXs sample data itself is installed on an invisible, protected part of the disk. To use the EXs, you’ll load its associated files (.KSC, PCG etc.); for the location of these files, see the documentation of the specific EXs.

Using the newly installed EXs

To use the new EXs:

1. Load the newly installed .PCG and .KSC files. Make sure to back up any sounds before over - writing them in memory.

As default, programs EXs178 will load to the bank **U-GG**.

Programs of EXs 178 Guitar Collection require the factory preload sounds.

Global “0-3: KSC Auto - Load”

Global “0-4: Sample Management”

Disk mode menu command “Load .PCG”

Disk mode menu command “Load .KSC”

Authorization

If an authorization code is required, the EXs will work in demo mode, fading in and out, until the code is purchased and entered into the KRONOS. For more information, see “Global P6: Options Info”.

New programs are installed in bank U-GG. Program & Multisample List:

No Program	Patch Name	Category	No Program	Patch Name	Category
U-GG000	Touch After Ac Guitar	Guitar/Plucked	U-GG041	Chorus 4U	Guitar/Plucked
U-GG001	Seamless Nylons	Guitar/Plucked	U-GG042	Flanger Touch	Guitar/Plucked
U-GG002	Nylon Dreams	Guitar/Plucked	U-GG043	Sharp Piezzo	Guitar/Plucked
U-GG003	Acoustic Guitar	Guitar/Plucked	U-GG044	Retro Tremolo	Guitar/Plucked
U-GG004	Nylon String Guitar	Guitar/Plucked	U-GG045	Clean and Pure	Guitar/Plucked
U-GG005	Small Nylon Guitar	Guitar/Plucked	U-GG046	Clean and Cleaner	Guitar/Plucked
U-GG006	Nylon Camp Fire	Guitar/Plucked	U-GG047	No Amp Guitar	Guitar/Plucked
U-GG007	Classic Clean	Guitar/Plucked	U-GG048	Playable One	Guitar/Plucked
U-GG008	Spanish Acoustic Guitar	Guitar/Plucked	U-GG049	Deli Jazzy Guitar	Guitar/Plucked
U-GG009	Sexy Nylons	Guitar/Plucked	U-GG050	Phaser Bluesy Guitar	Guitar/Plucked
U-GG010	Creamy Nylon	Guitar/Plucked	U-GG051	Note Shift Guitar	Guitar/Plucked
U-GG011	Ordinary Acoustic Guitar	Guitar/Plucked	U-GG052	Electric guitar for You	Guitar/Plucked
U-GG012	Gentle guitar	Guitar/Plucked	U-GG053	Dynamic El Guitar	Guitar/Plucked
U-GG013	Playful acoustic guitar	Guitar/Plucked	U-GG054	Bluesy Groove Guitar	Guitar/Plucked
U-GG014	Steel Acoustic VeloGliss	Guitar/Plucked	U-GG055	Phaser Space	Guitar/Plucked
U-GG015	Calm Guitar Duo	Guitar/Plucked	U-GG056	Sharp'n Crisp	Guitar/Plucked
U-GG016	Solo Acoustic Guitar	Guitar/Plucked	U-GG057	80's Guitar Retro	Guitar/Plucked
U-GG017	Background 12 String Gtr	Guitar/Plucked	U-GG058	Big Clean Guitar	Guitar/Plucked
U-GG018	Wide 12 String Guitar	Guitar/Plucked	U-GG059	Nice 80's Guitar	Guitar/Plucked
U-GG019	So many guitars	Guitar/Plucked	U-GG060	Detuned Guitar	Guitar/Plucked
U-GG020	Bright & Classy	Guitar/Plucked	U-GG061	Play with Delay	Guitar/Plucked
U-GG021	Wide 12 Stringed	Guitar/Plucked	U-GG062	No play with Delay	Guitar/Plucked
U-GG022	Wide spread guitar	Guitar/Plucked	U-GG063	Piezzzo Guitar	Guitar/Plucked
U-GG023	Classic'n Smooth	Guitar/Plucked	U-GG064	Velocity-Check Guitar	Guitar/Plucked
U-GG024	Tensed Strings	Guitar/Plucked	U-GG065	Clean or else	Guitar/Plucked
U-GG025	Look for split point	Guitar/Plucked	U-GG066	Happy Electric Guitar	Guitar/Plucked
U-GG026	Ambient Acoustic Guitar	Guitar/Plucked	U-GG067	Small joy to change me	Guitar/Plucked
U-GG027	Strange strumming	Guitar/Plucked	U-GG068	Two many Guitars	Guitar/Plucked
U-GG028	Fragolet Acoustic Guitar	Guitar/Plucked	U-GG069	All at once	Guitar/Plucked
U-GG029	WahWah Gtr	Guitar/Plucked	U-GG070	Muted for All	Guitar/Plucked
U-GG030	Icy Cold Guitar	Guitar/Plucked	U-GG071	Upside down	Guitar/Plucked
U-GG031	My Studio Guitar	Guitar/Plucked	U-GG072	Wait for Me Clean Gtr	Guitar/Plucked
U-GG032	Just a guitar with ...	Guitar/Plucked	U-GG073	Wait for me	Guitar/Plucked
U-GG033	Jazzyy	Guitar/Plucked	U-GG074	Wait for me - I'm coming	Guitar/Plucked
U-GG034	Rotary Guitar	Guitar/Plucked	U-GG075	Classic Rewind (8 sec.)	Guitar/Plucked
U-GG035	Rich Guitar	Guitar/Plucked	U-GG076	Auto-Reverse Deck	Guitar/Plucked
U-GG036	Ducky Lucky	Guitar/Plucked	U-GG077	Joy to mute me (down)	Guitar/Plucked
U-GG037	E.Guitar	Guitar/Plucked	U-GG078	Fragolet EL	Guitar/Plucked
U-GG038	Gliss'n Echo	Guitar/Plucked	U-GG079	Guitarist' Joy Effects	Guitar/Plucked
U-GG039	Bi-Chorus Guitar	Guitar/Plucked	U-GG080	Mike`s fav guitar sound	Guitar/Plucked
U-GG040	Wah auto wah	Guitar/Plucked	U-GG081	JuicyHeavyLead Gtr JS+-Y	Guitar/Plucked

U-GG082	Eddie's calling	Guitar/Plucked	U-GG105	Metal Guitar2 SW2Up/Down	Guitar/Plucked
U-GG083	ScreamingTubeSolo Guitar	Guitar/Plucked	U-GG106	Metal Guitar3 SW2Up/Down	Guitar/Plucked
U-GG084	Joystick Fun	Guitar/Plucked	U-GG107	FX SW2 Up/Down	Guitar/Plucked
U-GG085	Power Lead and more	Guitar/Plucked	U-GG108	FX MENU	SFX
U-GG086	Overdrive Dirty Tracks	Guitar/Plucked	U-GG109	FX MENU RANDOM (1 note)	SFX
U-GG087	Overdrive Lead Hero	Guitar/Plucked	U-GG110	Detuned Bass1	Bass/Synth Bass
U-GG088	Guitarist Dream AC15	Guitar/Plucked	U-GG111	Classic Bass1	Bass/Synth Bass
U-GG089	Overdrive Lead Delay	Guitar/Plucked	U-GG112	Marcus Bass	Bass/Synth Bass
U-GG090	Lead me there	Guitar/Plucked	U-GG113	Exact Precision Bass	Bass/Synth Bass
U-GG091	Talk to me (Ribbon)	Guitar/Plucked	U-GG114	Bass Me	Bass/Synth Bass
U-GG092	Crazy Guitar FXs SW2 off	Guitar/Plucked	U-GG115	Just Bassy	Bass/Synth Bass
U-GG093	SoloDistGuitar SW2 Bent	Guitar/Plucked	U-GG116	Velocity Slap Bass 1	Bass/Synth Bass
U-GG094	Dirty'n Ugly	Guitar/Plucked	U-GG117	Velocity Slap Bass 2	Bass/Synth Bass
U-GG095	Multieffect Joy Y-	Guitar/Plucked	U-GG118	Velocity Slap Bass 3	Bass/Synth Bass
U-GG096	Hello Eddie	Guitar/Plucked	U-GG119	Fast Bass	Bass/Synth Bass
U-GG097	Effect Chain Guitar	Guitar/Plucked	U-GG120	Try Me Bass	Bass/Synth Bass
U-GG098	Say hi to Ritchi	Guitar/Plucked	U-GG121	In Your Face Bass	Bass/Synth Bass
U-GG099	Guitarist Black SW2 Bent	Guitar/Plucked	U-GG122	Fretles Bass	Bass/Synth Bass
U-GG100	Guitar or else	Guitar/Plucked	U-GG123	BassIC	Bass/Synth Bass
U-GG101	Solo and key-off effect	Guitar/Plucked	U-GG124	Feedback Bass	Bass/Synth Bass
U-GG102	Misty Guitar	Guitar/Plucked	U-GG125	Don't Slap Me Anymore 1	Bass/Synth Bass
U-GG103	Key-off Guitar 1	Guitar/Plucked	U-GG126	Don't Slap Me Anymore 2	Bass/Synth Bass
U-GG104	Metal Guitar1 SW2 FX	Guitar/Plucked	U-GG127	Fragolet Bass	Bass/Synth Bass

Multisamples :

MULTISAMPLE LIST :		
0	Acoustic Guitar	38 Blues Guitar FF
1	Nylon A	39 Blues Guitar MF
2	Nylon B	40 Blues Guitar Mute
3	Steel AC Guitar 20	41 Gold Guitar
4	Steel AC Guitar 127	42 Blues FF
5	12 ac 1	43 Blues MF
6	Nylon F	44 Fragolet bass
7	Nylon K	45 Podloga 1_4
8	Acoustic FX	46 Podloga 1_4 up
9	Fragolet AC	47 Modulation Guitar El
10	El Dry 1	48 Piezo 2
11	El Dry 2	49 Podloga F5_1
12	El Dry 3	50 Podloga 8_2A
13	El Dry 4	51 Podloga 8_2B
14	El Dry 5	52 FX El 1
15	El Dry 6	53 Gliss 3_3
16	El Dry 7	54 Gliss down
17	El Dry 8	55 Big Clea
18	El Dry 9 Octa	56 Guitar Clean 60
19	El Dry 10	57 Fragolet El
20	Metal Guitar	58 Guitar 3_3
21	Metal Guitar Pitch Down	59 Guitar GB pp
22	Overdrive lead	60 Guitar GB pd
23	FX El Dry	61 Guitar GB kd
24	UP FX	62 Guitar GB FF
25	Gliss 3_4 Dow	63 FX El 2
26	Gliss 3_4 Up	64 Bass GM pp
27	ZZ Short	65 Bass GM Klang1
28	Podloga 9_4	66 Bass GM Klang2
29	Bent FX	Bass GM Klang3
30	Piezo finger	68 Bass GM K
31	El Piezo F	69 Bass GB
32	El Piezo FF	70 Bass GB Klang4
33	Piezo PP	71 Fretless Bass
34	Clean Guitar	72 Bass GB Klang5
35	Clean Guitar 2 FF	73 Bass GB Klang6
36	Clean Guitar 2 MF	74 Pick GB Bass
37	Clean Guitar 2 Mute	

New WaveSequence are installed in bank U-GG.

WaveSequence List :			
U-GG000	GUITAR GB MIX	U-GG016	GOLDCHAIR
U-GG001	BLUES	U-GG017	MUTE
U-GG002	GUITAR GB pp	U-GG018	BLUES FF
U-GG003	GUITAR GB kd	U-GG019	BLUES MF
U-GG004	GUITAR GB pd	U-GG020	STEEL AC
U-GG005	GUITAR GB ff	U-GG021	BASS GM PP
U-GG006	NYLON A	U-GG022	BASS GM K
U-GG007	NYLON B	U-GG023	BASS GM SLAMP 1
U-GG008	NYLON C	U-GG024	BASS GM SLAMP 2
U-GG009	ACOUSTIC GUITAR	U-GG025	FRETLESS BASS
U-GG010	CLEAN GUITAR	U-GG026	ZZ SHORT
U-GG011	ACOUSTIC FRAGOLET	U-GG027	MODULATION GUITAR
U-GG012	BIG CLEAN	U-GG028	GUITAR SEQUENCE 1
U-GG013	STEEL AC 12	U-GG029	GUITAR SEQUENCE 2
U-GG014	GUITAR 3-3	U-GG030	GUITAR SEQUENCE 3
U-GG015	EL DRY	U-GG031	FX GUITAR

The following instructions are copied from the Kronos Parameter Guide for your convenience:

Uninstall EXs

Optional EXs may be uninstalled to reclaim space on the internal disk(s). To do so:

1. Go to the Global P6: Options Info page.

2. In the list of Installed Options, select the EXs that you'd like to remove.

3. Select the Uninstall EXs command from the menu.

A dialog box will appear: Uninstall [EXs name and number]

Delete all of the option's EXs Samples and Multisamples?

4. Press OK to continue. Another dialog box will appear, showing that the uninstall is in progress. After the uninstall is complete, a third dialog box will appear: [EXs name and number] sample data deleted.

Related PCG, KSC etc. may remain; delete manually if desired. Only the EXs Multisamples and Drum Samples are removed from the disk. KSC and PCG files can be edited, and so they might contain your personal data; to avoid inadvertently affecting your data, these files are left untouched.

5. Press OK to continue.

6. If you like, delete the related PCG and KSC files manually in Disk mode.